


Readme

This program is developed to be run on 11 computers: 1 server and 10 clients.

TO INSTALL THE PROGRAM

SERVER


Launch on the Server the install shield setup.exe that you will find in the Server folder.



Follow all the Instructions reported on your video accepting all default options.

CLIENT

Launch on each of Client' computer the install shield setup.exe that you will find in the folder Client.




Follow all the Instructions showed on your video accepting all default options. Please make sure to put in the due box *Nome utente* uno of the 10 names yet configured in the Server program (i. e. Cacciavite, Casa, CD, Cellulare, Chiave, Clessidra, Cubo, Floppy, Fotografia, Goccia).

BE CAREFUL: do not put the same name on more than one computer.

CONFIGURATION

SERVER


Open with a text editor the file `CIDaServer.exe.config` that you will find in the install folder of the program and do modify the value of the box Remote server inserting the IP address of the computer Server.



```
113 <add key="Client12" value="Pc" />
114 <add key="Client12_end" value="300" />
115 <add key="Client12_endx" value="0" />
116 <add key="Client12_endy" value="20" />
117 <add key="Client12_defpx" value="0" />
118 <add key="Client12_defqx" value="0" />
119 <add key="Client12_defpy" value="0" />
120 <add key="Client12_defqy" value="0" />
121 <add key="Client13" value="Matita" />
122 <add key="Client13_end" value="300" />
123 <add key="Client13_endx" value="20" />
124 <add key="Client13_endy" value="0" />
125 <add key="Client13_defpx" value="0" />
126 <add key="Client13_defqx" value="0" />
127 <add key="Client13_defpy" value="0" />
128 <add key="Client13_defqy" value="0" />
129 <add key="Rounds" value="19" />
130 <add key="TrialRounds" value="2" />
131 <add key="Server" value="RemoteServer" />
132 <add key="LocalHost" value="127.0.0.1" />
133 <add key="LocalServer" value="172.16.48.50" />
134 <add key="RemoteServer" value="172.16.48.100" />
135 <add key="ServerPort" value="8085" />
136 <add key="DebugMode" value="false" />
137 <add key="DisplayDialogs" value="true" />
138 <add key="WindowState" value="1" />
139 <add key="DefaultTreatment" value="0" />
140 <add key="SessionTime" value="240" />
141 <add key="English" value="0" />
142 </appSettings>
143 </configuration>
```

CLIENT

Open with a text editor the file `CIDaClient.exe.config` that you will find in the install folder of the program and do modify the value of the box Remote server inserting the IP address of the computer Server.



```
1 <?xml version="1.0" encoding="utf-8" ?>
2 <configuration>
3   <appSettings>
4     <add key="AppName" value="CIDaTreatments - Client" />
5     <add key="Server" value="RemoteServer" />
6     <add key="LocalHost" value="127.0.0.1" />
7     <add key="LocalServer" value="172.16.48.50" />
8     <add key="RemoteServer" value="172.16.48.100" />
9     <add key="ServerPort" value="8085" />
10    <add key="DebugMode" value="false" />
11    <add key="WindowState" value="2" />
12    <add key="DisplayDialogs" value="true" />
13    <add key="IntroTime" value="60" />
14    <add key="MessageTime" value="5" />
15    <add key="PayoffTime" value="20" />
16    <add key="Username" value="Cacciavite" />
17    <add key="English" value="0" />
18  </appSettings>
19 </configuration>
```


BE CAREFUL: the IP address that you will insert in the configuration file of each Client program should be the same of the one that you inserted in the configuration of the Server program.

TO START

SERVER

Launch the program using the connection provided on the desktop or in the menu start otherwise.

Choose one among the 4 types of Treatments provided and wait until all Clients are connected



Launch the selected treatment from the menu Trattamento.


At the end of each Treatment it will be possible to find all the data to save in the file CIDaTreatments.mdb in the Data folder that you will find in the folder of installation of the program.

CLIENT

Launch the program using the connection provided on the desktop or in the menu start otherwise.

Wait to be connected to the Server.

Wait the begin of the selected Treatment.



Follow the Instructions for the experiment.